

<pre>##R01## conf t ! router ospf 1 router-id 1.1.1.1 ! area 1 nssa area 1 nssa default-information-originate ! network 1.1.1.1 0.0.0.0 area 0 network 192.168.15.1 0.0.0.0 area 0 network 192.168.51.1 0.0.0.0 area 0 network 192.168.12.1 0.0.0.0 area 1 network 192.168.13.1 0.0.0.0 area 1 ! end</pre>	<pre>##R05## conf t ! router ospf 1 router-id 5.5.5.5 ! area 2 nssa no-summary ! network 5.5.5.5 0.0.0.0 area 0 network 192.168.15.5 0.0.0.0 area 0 network 192.168.51.5 0.0.0.0 area 0 network 192.168.56.5 0.0.0.0 area 2 network 192.168.57.5 0.0.0.0 area 2 ! end</pre>
<pre>##R02## conf t ! router ospf 1 router-id 2.2.2.2 ! area 1 nssa ! network 2.2.2.2 0.0.0.0 area 1 network 192.168.12.2 0.0.0.0 area 1 redistribute eigrp 100 subnets ! ! router eigrp 100 eigrp router-id 2.2.2.2 network 2.2.2.2 0.0.0.0 network 192.168.24.2 0.0.0.0 redistribute ospf 1 metric 10000 10 255 1 1500 ! end</pre>	<pre>##R06## conf t ! router ospf 1 ! area 2 nssa ! router-id 6.6.6.6 network 6.6.6.6 0.0.0.0 area 2 network 192.168.56.6 0.0.0.0 area 2 network 192.168.68.6 0.0.0.0 area 2 ! end</pre>
<pre>##R03## conf t ! router ospf 1 router-id 3.3.3.3 ! area 1 nssa ! network 3.3.3.3 0.0.0.0 area 1 network 192.168.13.3 0.0.0.0 area 1 ! end</pre>	<pre>##R07## conf t ! router ospf 1 router-id 7.7.7.7 ! area 2 nssa ! network 7.7.7.7 0.0.0.0 area 2 network 192.168.57.7 0.0.0.0 area 2 network 192.168.78.7 0.0.0.0 area 2 ! end</pre>
<pre>##R04## conf t ! router eigrp 100 eigrp router-id 4.4.4.4 network 4.4.4.4 0.0.0.0 network 192.168.24.4 0.0.0.0 network 172.16.0.0 0.0.255.255 ! end</pre>	<pre>##R08## conf t ! route-map INT-SUZ deny 10 match interface Ethernet0/0 Serial1/0 ! route-map INT-SUZ permit 20 ! router ospf 1 router-id 8.8.8.8 ! area 2 nssa ! network 8.8.8.8 0.0.0.0 area 2 network 192.168.68.8 0.0.0.0 area 2 network 192.168.78.8 0.0.0.0 area 2 redistribute connected route-map INT-SUZ subnets ! end</pre>